

NAME

FingerprintsSDFFileIO

SYNOPSIS

```
use FileIO::FingerprintsSDFFileIO;

use FileIO::FingerprintsSDFFileIO qw(:all);
```

DESCRIPTION

FingerprintsSDFFileIO class provides the following methods:

new, GetCompoundString, GetFingerprints, GetFingerprintsString, IsFingerprintsDataValid, IsFingerprintsFileDataValid, IsFingerprintsSDFFile, Next, Read, SetBitStringFormat, SetBitsOrder, SetCompoundIDMode, SetCompoundString, SetDetailLevel, SetFingerprints, SetFingerprintsString, SetFingerprintsStringMode, SetVectorStringFormat, WriteFingerprints, WriteFingerprintsString

The following methods can also be used as functions:

IsFingerprintsSDFFile

FingerprintsSDFFileIO class is derived from *FileIO* class and uses its methods to support generic file related functionality.

The fingerprints SD file format with .sdf or .sd file extensions supports two types of fingerprints string data: fingerprints bit-vectors and fingerprints vector strings. The fingerprints string data is treated as value of a fingerprints data field label in a SD file.

Example of SD file format containing fingerprints string data:

```
... ..
... ..
$$$$
... ..
... ..
... ..
41 44 0 0 0 0 0 0 0 0 0999 V2000
-3.3652 1.4499 0.0000 C 0 0 0 0 0 0 0 0 0 0 0
... ..
2 3 1 0 0 0 0
... ..
M END
> <CmpdID>
Test

> <PathLengthFingerprints>
FingerprintsBitVector;PathLengthBits:AtomicInvariantsAtomTypes:MinLength:MaxLength8;1024;HexadecimalString;Ascending;9c8460989ec8a49913991a6603130b0a19e8051c89184414953800cc2151082844a201042800130860308e8204d402800831048940e44281c00060449a5000ac80c894114e006321264401600846c05016446208190410805000304a10205b0100e04c0038ba0fad0209c0ca8b1200012268b61c0026a
aa0660a11014a011d46

$$$$
... ..
... ..
```

The current release of MayaChemTools supports the following types of fingerprint bit-vector and vector strings:

```
FingerprintsVector;AtomNeighborhoods:AtomicInvariantsAtomTypes:MinRadius0:MaxRadius2;41;AlphaNumericalValues;ValuesString;NR0-C.X1.B01.H3-ATC1:NR1-C.X3.B03.H1-ATC1:NR2-C.X1.B01.H3-ATC1:NR2-C.X3.B04-ATC1 NR0-C.X1.B01.H3-ATC1:NR1-C.X3.B03.H1-ATC1:NR2-C.X1.B01.H3-ATC1:NR2-C.X3.B04-ATC1 NR0-C.X2.B02.H2-ATC1:NR1-C.X2.B02.H2-ATC1:NR1-C.X3.B03.H1-ATC1:NR2
```



```
FingerprintsBitVector;MACCSKeyBits;166;BinaryString;Ascending;00000000  
00000000000000000000000000000000100100001001000000001001000000001100  
01001010101111000110110001001101100000110111101001101111111111101111  
1111111111110111000
```

```
FingerprintsVector;MACCSKeyCount;l66;OrderedNumericalValues;ValuesStr  
ing;0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0  
0 0 0 0 0 0 0 0 0 1 0 0 3 0 0 0 0 4 0 0 2 0 0 0 0 0 0 0 0 2 0 0 2 0 0 0 0  
0 0 0 0 0 1 8 0 0 0 1 0 0 1 0 1 0 1 3 1 3 1 0 0 0 1 2 0 11 1 0 0 0  
5 0 0 1 2 0 1 1 0 0 0 0 0 1 1 0 1 1 1 0 4 0 1 1 0 4 6 1 1 1 2 1 1  
3 5 2 2 0 5 3 5 1 1 2 5 1 2 1 2 4 8 3 5 5 2 2 0 3 5 4 1
```

```
FingerprintsBitVector;PathLengthBits:AtomicInvariantsAtomTypes:MinLength1:MaxLength8;1024;BinaryString;Ascending;0010000100110101010110001100100010101011000101001011100110001000010001001101000001001001001001000010110010010000010010101001001001100110110011011011011011000000010110110110010010000010001010100000101110011011011011011000000010110110110011011000110000000100010000110000110001101100001000001000100000000...
```

```
FingerprintsVector;PathLengthCount:MMFF94AtomTypes:MinLength1:MaxLength
h8;463;NumericalValues;IDsAndValuesPairsString;C5A 2 C5B 2 C=ON 1 CB 1
8 COO 1 CR 9 F 1 N5 1 NC=O 1 O=CN 1 O=CO 1 OC=O 1 OR 2 C5A:C5B 2 C5A:N
5 2 C5ACB 1 C5ACR 1 C5B:C5B 1 C5BC=ON 1 C5BCB 1 C=ON=O=CN 1 C=ONNC=O 1
CB:CB 18 CBF 1 CBNC=O 1 COO=O=CO 1 COOCR 1 COOOC=O 1 CRCR 7 CRN5 1 CR
OR 2 C5A:C5B:C5B 2 C5A:C5BC=ON 1 C5A:C5BCB 1 C5A:N5:C5A 1 C5A:N5CR
```

```
FingerprintsVector;TopologicalAtomPairs;FunctionalClassAtomTypes;MinDistance:MaxDistance10;144;NumericalValues;IDsAndValuesString;Ar-D1-Ar
```

```
Ar-D1-Ar.HBA Ar-D1-HBD Ar-D1-Hal Ar-D1-None Ar.HBA-D1-None HBA-D1-NI H
BA-D1-None HBA.HBD-D1-NI HBA.HBD-D1-None HBD-D1-None NI-D1-None No...;
23 2 1 1 2 1 1 1 1 2 1 1 7 28 3 1 3 2 8 2 1 1 1 5 1 5 24 3 3 4 2 13 4
1 1 4 1 5 22 4 4 3 1 19 1 1 1 1 1 2 2 3 1 1 8 25 4 5 2 3 1 26 1 4 1 ...
```

```
FingerprintsVector;TopologicalAtomTorsions:AtomicInvariantsAtomTypes;3
3;NumericalValues;IDsAndValuesString;C.X1.BO1.H3-C.X3.BO3.H1-C.X3.BO4-
C.X3.BO4 C.X1.BO1.H3-C.X3.BO3.H1-C.X3.BO4-N.X3.BO3 C.X2.BO2.H2-C.X2.BO
2.H2-C.X3.BO3.H1-C.X2.BO2.H2 C.X2.BO2.H2-C.X2.BO2.H2-C.X3.BO3.H1-O...;
2 2 1 1 2 2 1 1 3 4 4 8 4 2 2 6 2 2 1 2 1 1 2 1 1 2 6 2 4 2 1 3 1
```

```
FingerprintsVector;TopologicalAtomTorsions:EStateAtomTypes;36;Numerica
lValues;IDsAndValuesString;aaCH-aaCH-aaCH-aaCH aaCH-aaCH-aaCH-aasC aaC
H-aaCH-aasC-aaCH aaCH-aaCH-aasC-aasC aaCH-aaCH-aasC-sF aaCH-aaCH-aasC-
ssNH aaCH-aasC-aasC-aasC aaCH-aasC-aasC-aasN aaCH-aasC-ssNH-dssC a...;
4 4 8 4 2 2 6 2 2 2 4 3 2 1 3 3 2 2 2 1 2 1 1 1 2 1 1 1 1 1 1 1 2 1 1 2
```

```
FingerprintsVector;TopologicalAtomTriplets:AtomicInvariantsAtomTypes:M
inDistance1;MaxDistance10;3096;NumericalValues;IDsAndValuesString;C.X1
.BO1.H3-D1-C.X1.BO1.H3-D1-C.X3.BO3.H1-D2 C.X1.BO1.H3-D1-C.X2.BO2.H2-D1
0-C.X3.BO4-D9 C.X1.BO1.H3-D1-C.X2.BO2.H2-D3-N.X3.BO3-D4 C.X1.BO1.H3-D1
-C.X2.BO2.H2-D4-C.X2.BO2.H2-D5 C.X1.BO1.H3-D1-C.X2.BO2.H2-D6-C.X3...;
1 2 2 2 2 2 2 8 8 4 8 4 4 2 2 2 2 4 2 2 2 4 2 2 2 2 1 2 2 4 4 4 2 2
2 4 4 4 8 4 4 2 4 4 4 2 4 4 2 2 2 2 2 2 2 1 2 2 2 2 2 2 2 2 2 8...
```

```
FingerprintsVector;TopologicalAtomTriplets:SYBYLAtomTypes:MinDistance1
:MaxDistance10;2332;NumericalValues;IDsAndValuesString;C.2-D1-C.2-D9-C
.3-D10 C.2-D1-C.2-D9-C.ar-D10 C.2-D1-C.3-D1-C.3-D2 C.2-D1-C.3-D10-C.3-
D9 C.2-D1-C.3-D2-C.3-D3 C.2-D1-C.3-D2-C.ar-D3 C.2-D1-C.3-D3-C.3-D4 C.2
-D1-C.3-D3-N.ar-D4 C.2-D1-C.3-D3-O.3-D2 C.2-D1-C.3-D4-C.3-D5 C.2-D1-C.
3-D5-C.3-D6 C.2-D1-C.3-D5-O.3-D4 C.2-D1-C.3-D6-C.3-D7 C.2-D1-C.3-D7...
```

```
FingerprintsVector;TopologicalPharmacophoreAtomPairs:ArbitrarySize:Min
Distance1;MaxDistance10;54;NumericalValues;IDsAndValuesString;H-D1-H H
-D1-NI HBA-D1-NI HBD-D1-NI H-D2-H H-D2-HBA H-D2-HBD HBA-D2-HBA HBA-D2-
HBD H-D3-H H-D3-HBA H-D3-HBD H-D3-NI HBA-D3-NI HBD-D3-NI H-D4-H H-D4-H
BA H-D4-HBD HBA-D4-HBA HBA-D4-HBD HBD-D4-HBD H-D5-H H-D5-HBA H-D5-...;
18 1 2 1 22 12 8 1 2 18 6 3 1 1 1 22 13 6 5 7 2 28 9 5 1 1 1 36 16 10
3 4 1 37 10 8 1 35 10 9 3 3 1 28 7 7 4 18 16 12 5 1 2 1
```

```
FingerprintsVector;TopologicalPharmacophoreAtomPairs:FixedSize:MinDist
ance1;MaxDistance10;150;OrderedNumericalValues;ValuesString;18 0 0 1 0
0 0 2 0 0 1 0 0 0 0 22 12 8 0 0 1 2 0 0 0 0 0 0 0 0 18 6 3 1 0 0 0 1
0 0 1 0 0 0 0 22 13 6 0 0 5 7 0 0 2 0 0 0 0 0 28 9 5 1 0 0 0 1 0 0 1 0
0 0 0 36 16 10 0 0 3 4 0 0 1 0 0 0 0 0 37 10 8 0 0 0 0 1 0 0 0 0 0 0
0 35 10 9 0 0 3 3 0 0 1 0 0 0 0 0 28 7 7 4 0 0 0 0 0 0 0 0 0 0 0 18...
```

```
FingerprintsVector;TopologicalPharmacophoreAtomTriplets:ArbitrarySize:
MinDistance1;MaxDistance10;696;NumericalValues;IDsAndValuesString;Ar1-
Ar1-Ar1 Ar1-Ar1-H1 Ar1-Ar1-HBA1 Ar1-Ar1-HBD1 Ar1-H1-H1 Ar1-H1-HBA1 Ar1
-H1-HBD1 Ar1-HBA1-HBD1 H1-H1-H1 H1-H1-HBA1 H1-H1-HBD1 H1-HBA1-HBA1 H1-
HBA1-HBD1 H1-HBA1-NI1 H1-HBD1-NI1 HBA1-HBA1-NI1 HBA1-HBD1-NI1 Ar1-...;
46 106 8 3 83 11 4 1 21 5 3 1 2 2 1 1 1 100 101 18 11 145 132 26 14 23
28 3 3 5 4 61 45 10 4 16 20 7 5 1 3 4 5 3 1 1 1 1 5 4 2 1 2 2 2 1 1 1
119 123 24 15 185 202 41 25 22 17 3 5 85 95 18 11 23 17 3 1 1 6 4 ...
```

```
FingerprintsVector;TopologicalPharmacophoreAtomTriplets:FixedSize:MinD
istance1;MaxDistance10;2692;OrderedNumericalValues;ValuesString;46 106
8 3 0 0 83 11 4 0 0 0 1 0 0 0 0 0 0 0 0 21 5 3 0 0 1 2 2 0 0 1 0 0 0
0 0 0 1 0 0 1 0 0 0 0 0 0 0 0 0 0 0 100 101 18 11 0 0 145 132 26
```



```
'VectorStringFormat' => 'IDsAndValuesString',  
'FingerprintsLabel' => 'Fingerprints');
```

GetCompoundString

```
$CompoundString = $FingerprintsSDFFileIO->GetCompoundString();
```

Returns CompoundString for current compound.

GetFingerprints

```
$FingerprintsObject = $FingerprintsSDFFileIO->GetFingerprints();
```

Returns FingerprintsObject generated for current compound using fingerprints bit-vector or vector string data. The fingerprints object corresponds to any of the supported fingerprints such as PathLengthFingerprints, ExtendedConnectivity, and so on.

GetFingerprintsString

```
$FingerprintsString = $FingerprintsSDFFileIO->GetFingerprintsString();
```

Returns FingerprintsString for current compound.

IsFingerprintsDataValid

```
$Status = $FingerprintsSDFFileIO->IsFingerprintsDataValid();
```

Returns 1 or 0 based on whether FingerprintsObject is valid.

IsFingerprintsFileDataValid

```
$Status = $FingerprintsSDFFileIO->IsFingerprintsFileDataValid();
```

Returns 1 or 0 based on whether fingerprints file contains valid fingerprints data.

IsFingerprintsSDFile

```
$Status = $FingerprintsSDFFileIO->IsFingerprintsSDFile($FileName);  
$Status = FileIO::FingerprintsSDFFileIO::IsFingerprintsSDFile($FileName);
```

Returns 1 or 0 based on whether *FileName* is a SD file.

Next or Read

```
$FingerprintsSDFFileIO = $FingerprintsSDFFileIO->Next();  
$FingerprintsSDFFileIO = $FingerprintsSDFFileIO->Read();
```

Reads next available compound fingerprints in SD file, processes the data, generates appropriate fingerprints object, and returns FingerprintsSDFFileIO. The generated fingerprints object is available using method GetFingerprints.

SetBitStringFormat

```
$FingerprintsSDFFileIO->SetBitStringFormat($Format);
```

Sets bit string *Format* for fingerprints bit-vector string data in a SD file and returns FingerprintsSDFFileIO. Possible values for BitStringFormat: *BinaryString* or *HexadecimalString*.

SetBitsOrder

```
$FingerprintsSDFFileIO->SetBitsOrder($BitsOrder);
```

Sets *BitsOrder* for fingerprints bit-vector string data in SD file and returns FingerprintsSDFFileIO. Possible values for BitsOrder: *Ascending* or *Descending*.

SetCompoundIDMode

```
$FingerprintsSDFFileIO->SetCompoundIDMode($Mode);
```

Sets compound ID *Mode* for fingerprints bit-vector string data in a SD file and returns FingerprintsSDFFileIO. Possible values for CompoundIDMode: *DataField*, *MolName*, *LabelPrefix*, or

MolNameOrLabelPrefix.

SetCompoundString

```
$FingerprintsSDFFileIO->SetCompoundString($CompoundString);
```

Sets *CompoundString* and returns FingerprintsSDFFileIO.

SetDetailLevel

```
$FingerprintsSDFFileIO->SetDetailLevel($Level);
```

Sets details *Level* for generating diagnostics messages during SD file processing and returns FingerprintsSDFFileIO. Possible values: *Positive integers*.

SetFingerprints

```
$FingerprintsSDFFileIO->SetFingerprints($FingerprintsObject);
```

Sets *FingerprintsObject* for current data line and returns FingerprintsSDFFileIO.

SetFingerprintsString

```
$FingerprintsSDFFileIO->SetFingerprintsString($FingerprintsString);
```

Sets *FingerprintsString* for current data line and returns FingerprintsSDFFileIO.

SetFingerprintsStringMode

```
$FingerprintsSDFFileIO->SetFingerprintsStringMode($Mode);
```

Sets *FingerprintsStringMode* for SD file and returns FingerprintsFPFileIO. Possible values: *AutoDetect*, *FingerprintsBitVectorString*, or *FingerprintsVectorString*

SetVectorStringFormat

```
$FingerprintsSDFFileIO->SetVectorStringFormat($Format);
```

Sets *VectorStringFormat* for SD file and returns FingerprintsFPFileIO. Possible values: *IDsAndValuesString*, *IDsAndValuesPairsString*, *ValuesAndIDsString*, *ValuesAndIDsPairsString*.

WriteFingerprints

```
$FingerprintsFPFileIO->WriteFingerprints($FingerprintsObject,  
                                         $CompoundID);
```

Writes fingerprints string generated from *FingerprintsObject* object and other data including *CompoundID* to SD file and returns FingerprintsSDFFileIO.

WriteFingerprintsString

```
$FingerprintsSDFFileIO->WriteFingerprints($FingerprintsString,  
                                         $CompoundID);
```

Writes *FingerprintsString* and other data including *CompoundID* to SD file and returns FingerprintsSDFFileIO.

Caveats:

- o FingerprintsStringMode, BitStringFormat, BitsOrder, VectorStringFormat values are ignored during writing of fingerprints and it's written to the file as it is.
- o CompoundString is not checked to remove any existing fingerprints data

AUTHOR

Manish Sud <msud@san.rr.com>

SEE ALSO

FingerprintsTextFileIO.pm, FingerprintsFPFileIO.pm, SDFFileIO.pm

COPYRIGHT

Copyright (C) 2019 Manish Sud. All rights reserved.

This file is part of MayaChemTools.

MayaChemTools is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.